

B4x Booklets

B4A

B4i

B4J

Custom Views

Last update: 2017.02.15

Copyright: © 2017 Anywhere Software

Edition 1.0

1	General information	4
2	Class modules	5
2.1	Getting started	5
2.1.1	Adding a class module	6
2.1.2	Polymorphism	7
2.1.3	Self-reference	8
2.1.4	Activity object B4A only	9
3	Standard class	10
3.1	Standard class structure	10
4	CustomViews	12
4.1	CustomView class structure	12
4.1.1	Event declarations	13
4.1.2	Designer properties declarations	13
4.1.3	Global variable declarations	13
4.1.4	Initialization routine	14
4.1.5	Designer support routine	14
4.1.6	Routine to get the base Panel	15
4.2	Adding a custom view by code	15
4.3	Add properties	16
4.4	Custom view and custom properties in the Designer	17
4.5	Complie to a library	20
4.5.1	Library specific attributes	22
4.6	Program flow	24
4.7	Intellisense help	25
4.7.1	Comments before Sub Class_Globals	25
4.7.2	Comments before a routine	25
4.7.3	Comments before an event routine	26
4.8	Help tool	27
5	First example CustomButton	28
5.1	Event declarations	28
5.2	Custom properties for the Designer	28
5.3	Class help header	29
5.4	Global variables	29
5.5	Initialize routine	30
5.6	DesignerCreateView routine	31
5.7	Base_Resize routine B4i / B4J only	32
5.8	AddToParent routine	33
5.9	InitClass routine	34
5.10	Click / LongClick event routines	36
5.11	Property routines	37
5.12	Main code	38
5.12.1	Globals	38
5.12.2	Program start	39
5.13	Click event routine	40
5.14	Compile to Library	41
5.15	Use the library in a program	42
6	LimitBar	43
6.1	Event declaration	44
6.2	Custom properties for the Designer	44
6.3	Class help header	44
6.4	Global variables	45
6.5	Initialize routine	46
6.6	DesignerCreateView routine	47

6.7	Base_Resize routine B4i / B4J only	48
6.8	AddToParent routine	49
6.9	InitClass routine	50
6.10	InitCursors routine	53
6.11	Draw the background line	54
6.12	DrawCursors routine	55
6.13	Cursor moving	57
6.14	Properties	59
6.15	Compile to a Library	60
6.15.1	Using the library in a program	61

Main contributors: Klaus Christl (klaus) Erel Uziel (Erel).

1 General information

This guide is dedicated for more advanced users and treats the CustomView topic.

It covers B4A, B4i and B4J.

All the source code and files needed (layouts, images etc) for the example projects in this guide are included in the SourceCode folder.

For each project, there are three subfolders, one for each operating system.

- ▼ SourceCode
 - ▼ ClsCustomButton
 - > B4A
 - > B4i
 - > B4J
 - ▼ ClsLimitBar
 - > B4A
 - > B4i
 - > B4J
 - > Draw
 - > LblCustomButton
 - > LibLimitBar
 - > Person

2 Class modules

In B4x, you can use two types of Class Modules:

- Standard Class modules standard classes
- CustomView Class Modules specialized for custom views

2.1 Getting started

Classes definition from [Wikipedia](#):

In object-oriented programming, a class is a construct that is used to create instances of itself – referred to as class instances, class objects, instance objects or simply objects. A class defines constituent members which enable its instances to have state and behaviour. Data field members (member variables or instance variables) enable a class instance to maintain state. Other kinds of members, especially methods, enable the behaviour of a class instances. Classes define the type of their instances.

A class usually represents a noun, such as a person, place or thing, or something nominalized. For example, a "Banana" class would represent the properties and functionality of bananas in general. A single, particular banana would be an instance of the "Banana" class, an object of the type "Banana".

Let's start with an example, the source code: *Person* in the / Person folder.

In the Person module

```
'Class Person module
Sub Class_Globals
    Private FirstName, LastName As String
    Private BirthDate As Long
End Sub

Sub Initialize (aFirstName As String, aLastName As String, aBirthDate As Long)
    FirstName = aFirstName
    LastName = aLastName
    BirthDate = aBirthDate
End Sub

Public Sub GetName As String
    Return FirstName & " " & LastName
End Sub

Public Sub GetCurrentAge As Int
    Return GetAgeAt(DateTime.Now)
End Sub

Public Sub GetAgeAt(Date As Long) As Int
    Private diff As Long
    diff = Date - BirthDate
    Return Floor(diff / DateTime.TicksPerDay / 365)
End Sub
```

Main module.

```
Sub Activity_Create(FirstTime As Boolean)
    Private p As Person
    p.Initialize("John", "Doe", DateTime.DateParse("05/12/1970"))
    Log(p.GetCurrentAge)
End Sub
```

I will start by explaining the differences between classes, code modules and types.

Similar to types, classes are templates. From this template, you can instantiate any number of objects.

The type fields are similar to the classes global variables. However, unlike types which only define the data structure, classes also define the behaviour. The behaviour is defined in the classes' subs.


Unlike classes which are a template for objects, code modules are collections of subs. Another important difference between code modules and classes is that code modules always run in the context of the calling sub. The code module doesn't hold a reference to any context. For that reason it is impossible to handle events or use CallSub with code modules.

Classes store a reference to the context of the module that called the Initialize sub. This means that classes objects share the same life cycle as the module that initialized them.

2.1.1 Adding a class module

Adding a new or existing class module is done by choosing Project > Add New Module > Class module or Add Existing module.

Like other modules, classes are saved as files with *bas* extension.



There are two class module types:

[Standard Class](#)

[CustomView](#)

2.1.2 Polymorphism

Polymorphism allows you to treat different types of objects that adhere to the same interface in the same way.

B4x polymorphism is similar to the [Duck typing](#) concept.

As an example we will create two classes named: Square and Circle. Each class has a sub named Draw that draws the object to a canvas: Source code *Draw* in the Draw folder.

The code below is the B4A code.

```
'Class Square module
Sub Class_Globals
    Private mx, my, mWidth As Int
End Sub

'Initializes the object. You can add parameters to this method if needed.
Sub Initialize (Shapes As List, x As Int, y As Int, length As Int)
    mx = x
    my = y
    mLength = length
    Shapes.Add(Me)
End Sub

Sub Draw(c As Canvas)
    Private r As Rect
    r.Initialize(mx, my, mx + mLength, my + mLength)
    c.DrawRect(r, Colors.Red, False, 1dip)
End Sub

'Class Circle module
Sub Class_Globals
    Private mx, my, mRadius As Int
End Sub

'Initializes the object. You can add parameters to this method if needed.
Sub Initialize (Shapes As List, x As Int, y As Int, radius As Int)
    mx = x
    my = y
    mRadius = radius
    Shapes.Add(Me)
End Sub

Sub Draw(cvs As Canvas)
    cvs.DrawCircle(mx, my, mRadius, Colors.Blue, False, 1dip)
End Sub
```

In the main module, we create a list `Shapes` with Squares and Circles. We then go over the list and draw all the objects:

```
Sub Process_Globals
    Public Shapes As List
End Sub

Sub Globals
    Private cvs As Canvas
End Sub

Sub Activity_Create(FirstTime As Boolean)
    cvs.Initialize(Activity)
    Private Square1, Square 2 As Square
    Private Circle1 As Circle
    Shapes.Initialize
    Square1.Initialize(Shapes, 110dip, 110dip, 50dip)
    Square2.Initialize(Shapes, 10dip, 10dip, 100dip)
    Circle1.Initialize(Shapes, 50%x, 50%y, 100dip)

    DrawAllShapes
End Sub

Sub DrawAllShapes
    For i = 0 To Shapes.Size - 1
        CallSub2(Shapes.Get(i), "Draw", cvs)
    Next
    Activity.Invalidate
End Sub
```

As you can see, we do not know the specific type of each object in the list. We just assume that it has a Draw method that expects a single Canvas argument. Later we can easily add more types of shapes.

You can use the `SubExists` keyword to check whether an object includes a specific sub.

You can also use the `Is` keyword to check if an object is of a specific type.

2.1.3 Self-reference

The `Me` keyword returns a reference to the current object. `Me` keyword can only be used inside a class module.

Consider the above example. We have passed the `Shapes` list to the `Initialize` sub and then add each object to the list from the `Initialize` sub:

```
Sub Initialize (Shapes As List, x As Int, y As Int, radius As Int)
    mx = x
    my = y
    mRadius = radius
    Shapes.Add(Me)
End Sub
```

2.1.4 Activity object B4A only

This point is related to the Android Activities special life cycle.

Make sure to first read the [activities and processes life-cycle tutorial](#).

Android UI elements hold a reference to the parent activity. As the OS is allowed to kill background activities in order to free memory, UI elements cannot be declared as process global variables (these variables live as long as the process lives). Such elements are named Activity objects. The same is true for custom classes. If one or more of the class global variables is of a UI type (or any activity object type) then the class will be treated as an "activity object". The meaning is that instances of this class cannot be declared as process global variables.

3 Standard class

3.1 Standard class structure

Default template of a standard class:

B4A and B4i

```
Sub Class_Globals
```

```
End Sub
```

```
'Initializes the object. You can add parameters to this method if needed.
```

```
Public Sub Initialize
```

```
End Sub
```

B4J

```
Sub Class_Globals
```

```
Private fx As JFX
```

```
End Sub
```

```
'Initializes the object. You can add parameters to this method if needed.
```

```
Public Sub Initialize
```

```
End Sub
```

Only two routines are predefined:

Sub Class_Globals - This sub is similar to the Main Globals sub. These variables will be the class global variables (sometimes referred to instance variables or instance members).

In B4J, the fx library library is declared by default. You can remove it if not needed.

Sub Initialize - A class object must be initialized before you can call any other sub. Initializing an object is done by calling the Initialize sub. When you call Initialize you set the object's context (the parent object or service).

Note that you can modify this sub signature and add arguments as needed.

Example: Person class module

The source codes are in the Person folder.

The code is the same for all three B4x platforms (B4A, B4i, B4J).

```
'Class Person module
Sub Class_Globals
    Private mFirstName, mLastName As String
    Private mBirthDate As Long
End Sub

Sub Initialize (FirstName As String, LastName As String, BirthDate As Long)
    mFirstName = FirstName
    mLastName = LastName
    mBirthDate = BirthDate
End Sub

Public Sub GetName As String
    Return mFirstName & " " & mLastName
End Sub

Public Sub GetCurrentAge As Int
    Return GetAgeAt(DateTime.Now)
End Sub

Public Sub GetAgeAt(Date As Long) As Int
    Dim diff As Long
    diff = Date - mBirthDate
    Return Floor(diff / DateTime.TicksPerDay / 365)
End Sub
```

In the above code, we created a class named Person and later instantiate an object of this type in the main module:

```
Private p As Person
p.Initialize("John", "Doe", DateTime.DateParse("05/12/1970"))
Log(p.GetCurrentAge)
```

Calling initialize is not required if the object itself was already initialized:

```
Private p2 As Person
p2 = p 'both variables now point to the same Person object.
Log(p2.GetCurrentAge)
```

4 CustomViews

With custom view classes, you can create your own custom views which can be based on other standard or custom views, with more functions.

4.1 CustomView class structure

Several declarations and routines are predefined:

Default template of a CustomView class:

```
'Custom View class
#Event: ExampleEvent (Value As Int)
#DesignerProperty: Key: BooleanExample, DisplayName: Boolean Example, FieldType:
Boolean, DefaultValue: True, Description: Example of a boolean property.
#DesignerProperty: Key: IntExample, DisplayName: Int Example, FieldType: Int,
DefaultValue: 10, MinRange: 0, MaxRange: 100, Description: Note that MinRange and
MaxRange are optional.
#DesignerProperty: Key: stringWithListExample, DisplayName: String With List,
FieldType: String, DefaultValue: Sunday, List:
Sunday|Monday|Tuesday|Wednesday|Thursday|Friday|Saturday
#DesignerProperty: Key: StringExample, DisplayName: String Example, FieldType: String,
DefaultValue: Text
#DesignerProperty: Key: ColorExample, DisplayName: Color Example, FieldType: Color,
DefaultValue: 0xFFCFDCDC, Description: You can use the built-in color picker to find
the color values.
#DesignerProperty: Key: DefaultColorExample, DisplayName: Default Color Example,
FieldType: Color, DefaultValue: Null, Description: Setting the default value to Null
means that a nullable field will be displayed.
Sub Class_Globals
    Private mEventName As String 'ignore
    Private mCallback As Object 'ignore
    Private mBase As Panel
    Private Const DefaultColorConstant As Int = -984833 'ignore
End Sub

Public Sub Initialize (Callback As Object, EventName As String)
    mEventName = EventName
    mCallback = Callback
End Sub

Public Sub DesignerCreateView (Base As Panel, Lbl As Label, Props As Map)
    mBase = Base

End Sub

Public Sub GetBase As Panel
    Return mBase
End Sub
```

Additional routine in B4i and B4J:

```
Private Sub Base_Resize (Width As Double, Height As Double)

End Sub
```

This event routine is raised every time a resize occurs, device rotation in B4i or Form resize in B4J.

4.1.1 Event declarations

You should add Event declarations if you compile the custom view into a library. If the event routine has parameters, these must also be declared.

```
#Event: ExampleEvent (Value As Int)           important for intellisense.  
#RaisesSynchronousEvents: ExampleEvent       important for library compilation.
```

4.1.2 Designer properties declarations

```
#DesignerProperty: Key: BooleanExample, DisplayName: Boolean Example, FieldType:  
Boolean, DefaultValue: True, Description: Example of a boolean property.
```

You can add custom properties for the Designer.

More details in the chapter [Custom view in the Designer](#).

4.1.3 Global variable declarations

In this routine, you should declare all global variables used in the class.

The variables below are mandatory.

```
Sub Class_Globals  
    Private EventName As String 'ignore  
    Private Callback As Object 'ignore  
    Private mBase As Panel  
End Sub
```

EventName Event name used for the events in the code, same as for standard views.
Callback Module where the class is declared, used for event calls.
mBase Main panel of the custom view.

You can, if you want, change the name of the base panel.

What is this for 'ignore'?

It avoids a warning of the compiler that these variables are unused.

Variables only used in the class should be declared as **Private**.

If you want to have access to variables from other modules you must declare them as **Public**.

4.1.4 Initialization routine

The initialize routine initiates a new instance of the custom view.

```
Public Sub Initialize (Callback As Object, EventName As String)
    mCallback = Callback
    mEventName = EventName
End Sub
```

The two variables will be used to call event routines in the module where the custom view is initialized.

You should not modify its signature.

Example:

```
' if a callback routine exists in the calling module we call it
If SubExists(mCallback, mEventName & "_ValuesChanged") Then
    CallSub3(mCallback, mEventName & "_ValuesChanged", mLimit(0), mLimit(1))
End If
```

4.1.5 Designer support routine

This routine assures the support for the Designer, it is called directly after the Initialize routine of the custom view class.

You should not modify its signature.

```
Public Sub DesignerCreateView (Base As Panel, Lbl As Label, Props As Map)
    mBase = Base
End Sub
```

Base Is the base panel defined in the Designer, it holds the Left, Top, Width, Height and Parent properties of the custom view. The Base panel can be used or not.

Lbl Is a Label which holds all the text properties defined in the Designer. This Label can be used or not.

Props Is a Map holding additional properties. The ones you defined yourself in the designer properties definition.

4.1.6 Routine to get the base Panel

You can use this routine if you want to access the base panel / pane from other modules.

B4A / B4J

```
Public Sub GetBase As Panel
    Return mBase
End Sub
```

B4J

```
Public Sub GetBase As Pane
    Return mBase
End Sub
```

In the calling module:

```
Private pnlClass As Panel
pnlClass = clsTest.GetBase
```

```
Private pnlClass As Pane
pnlClass = clsTest.GetBase
```

4.2 Adding a custom view by code

To offer the possibility to add the custom view by code you must add a routine in the class which adds the custom view onto a parent view which can be either for:

B4A	an Activity or a Panel.	<code>Public Sub AddToParent(Parent As Activity,</code>
B4i	a Panel.	<code>Public Sub AddToParent(Parent As Panel,</code>
B4J	a Pane.	<code>Public Sub AddToParent(Parent As Pane,</code>

Example:

```
Public Sub AddToParent(Parent As Activity, Left As Int, Top As Int, Width As Int,
Height As Int)
    mBase.Initialize("mBase")
    Parent.AddView(mBase, Left, Top, Width, Height)
End Sub
```

Parent	is the parent view which can be an Activity, Panel or a Pane.
Left	is the Left property.
Top	is the Top property.
Width	is the Width property.
Height	is the Height property.

You can add other parameters or properties to the routine if necessary.

And in the calling module:

B4A / B4i

```
Private clsTest2 As ClsCustomView
```

```
clsTest2.Initialize(Me, "clsTest2")
clsTest2.AddToParent(MyPanel, 10dip, 10dip, 200dip, 50dip)
```

B4J Pane instead of Panel and no dip values.

```
Private clsTest2 As ClsCustomView
```

```
clsTest2.Initialize(Me, "clsTest2")
clsTest2.AddToParent(MyPane, 10, 10, 200, 50)
```

4.3 Add properties

Property routines can be added which work like any property of the standard views.

These properties can be read and or set.

To read a property you must add a routine beginning with `get`, **lower case** and the property name.

Examples:

Get the *Left* Property.

```
'gets the Left property
Public Sub getLeft As Int
    Return ltbPanelBack.Left
End Sub
```

Get the custom *Max* property.

```
'gets the Max value
Public Sub getMax As Int
    Return MaxValue
End Sub
```

To set a property you must add a routine beginning with `set`, **lower case** and the property name.

Examples:

Set the *Left* Property.

```
'sets the Left property
Public Sub setLeft(Left As Int)
    ltbPanelBack.Left = Left
End Sub
```

Set the custom *Max* property.

```
'sets the Max value
Public Sub setMax(MaxValue As Int)
    mMaxValue = MaxValue
    Scale = (x1 - x0) / mMaxValue
End Sub
```

If you define only a `get` routine the property is read only.

If you define only a `set` routine the property is write only.

If you define both a `set` and a `get` routine, the property is write and read.

Note:

`Public Sub setMax` and `Public Sub SetMax` are not the same!

`Public Sub setMax` is considered as a Property.

`Public Sub SetMax` is considered as a Public Subroutine.

4.4 Custom view and custom properties in the Designer

You can add code to make custom properties visible in the Designer.

The images below are from the DefaultLayout project in the SourceCode\DefaultLayout folder.

Only the B4A version.

On the top of the code you must include declaration lines. The default layout of a custom view class includes these example declarations:

```
#DesignerProperty: Key: BooleanExample, DisplayName: Boolean Example, FieldType:
Boolean, DefaultValue: True, Description: Example of a boolean property.
#DesignerProperty: Key: IntExample, DisplayName: Int Example, FieldType: Int,
DefaultValue: 10, MinRange: 0, MaxRange: 100, Description: Note that MinRange and
MaxRange are optional.
#DesignerProperty: Key: stringWithListExample, DisplayName: String With List,
FieldType: String, DefaultValue: Sunday, List:
Sunday|Monday|Tuesday|Wednesday|Thursday|Friday|Saturday
#DesignerProperty: Key: StringExample, DisplayName: String Example, FieldType: String,
DefaultValue: Text
#DesignerProperty: Key: ColorExample, DisplayName: Color Example, FieldType: Color,
DefaultValue: 0xFFCFDCDC, Description: You can use the built-in color picker to find
the color values.
#DesignerProperty: Key: DefaultColorExample, DisplayName: Default Color Example,
FieldType: Color, DefaultValue: Null, Description: Setting the default value to Null
means that a nullable field will be displayed.
```

Each property declaration is made of several fields, the following fields are required:

Key	Is the key value for the Map.
DisplayName	This will be used to get the value from the Props map.
FieldType	Is the name displayed in the Designer property grid.
DefaultValue	Is the type of the field.
	Possible values: String, Int, Double, Boolean or Color.
	Is the default value which is set in the Designer.


Optional fields:


Description	Is the explanation text displayed in the Designer.
MinRange / MaxRange	Minimum and maximum numeric values allowed.
List	A pipe () separated list of items from which the developer can choose (should be used with string fields).

In the Designer, you can add a CustomView like this:

Right click in the screen area, select Add View and select CustomView.

Select the custom from the list of available custom views *ClsCustomView* in the example.






In the Properties window, you find all the properties for the selected custom view. Imges B4A.

Custom properties:

Here we see the six custom properties declared on top of the Class code.

Example with the String With List property.



Common Properties:

The common properties like any view.

Text Style:

The properties are set to the Lb1 Label of the class.

Base Background:

Background of the base panel Base.

To access the custom properties you must use the Props Map in the **DesignerCreateView** routine.

Variable declaration:

```
Private BooleanTest As Boolean
Private IntTest As Int
Private Day As String
Private StringTest As String
Private ColorTest As Int
Private DefaultColorTest As Int
```

And the DesignerCreateView routine:

```
Public Sub DesignerCreateView (Base As Panel, Lbl As Label, Props As Map)
    mBase = Base

    BooleanTest = Props.Get("BooleanExample")
    IntTest = Props.Get("IntExample")
    Day = Props.Get("StringWithListExample")
    StringTest = Props.Get("StringExample")
    ColorTest = Props.Get("ColorExample")
    DefaultColorTest = Props.Get("DefaultColorExample")
End Sub
```

B4J the Base declaration is different, **Pane** instead of **Panel**.

```
Public Sub DesignerCreateView (Base As Pane, Lbl As Label, Props As Map)
```

You can get properties of the Base Panel / Pane like:

B4A / B4i / B4J

```
Private mWidth As Int
mWidth = Base.Width
```

```
Private mHeight As Int
mHeight = Base.Height
```

You can get text properties from the Lbl Label like:

B4A

```
Private mText As String
mText = Lbl.Text
```

```
Private mTextColor As Int
mTextColor = Lbl.TextColor
```

```
Private mTextSize As Float
mTextSize = Lbl.TextSize
```

B4i

```
Private mText As String
mText = Lbl.Text
```

```
Private mTextColor As Int
mTextColor = Lbl.TextColor
```

```
Private fnt As Font
Private mTextSize As Float
fnt = Lbl.Font
mTextSize = fnt.Size
```

B4J

```
Private mText As String
mText = Lbl.Text
```

```
Private mTextColor As Paint
mTextColor = Lbl.TextColor
```

```
Private mTextSize As Double
mTextSize = Lbl.TextSize
```

4.5 Compile to a library

In B4A, B4i and B4J you can compile your project, or part of it to a regular library.

Why should we compile a library?

- Break large projects into several smaller (more maintainable) projects.
- Build reusable components and use them from any number of projects.
- Share components with other developers without sharing the source code.
- Create different versions of your application (free, pro...) by referencing the same "core" library.

The output of library compilation is:

- Two files for B4A and B4J:
A jar file with the compiled code and a xml file that includes the metadata that is required by the IDE.
These two files are automatically saved in the additional libraries folders.
- Three files for B4i:
The xml file like above which is copied to the additional libraries folders.
And, .a and .h files are created in the Mac Libs folder.

You can exclude other modules as well with the ExcludeFromLibrary attribute.

```
#ExcludeFromLibrary: True
```

The Main module and the other excluded modules can be used to test the library.


You can reference the library from other projects and access the same functionality as in the original project.

Compiling to a library is quite simple.


Under Project menu there is the compile option - "Compile To Library (Alt + 5)".

When you choose this option all the modules **except** of the main activity are compiled into a library.


B4A



B4J




B4i



Note: If you are using the hosted builder then you need to first receive a permission to compile a specific library. Please contact support@basic4ppc.com and send your hosted builder id and the library name.

You find the hosted builder id in Tools / Build Server / Server Settings.



4.5.1 Library specific attributes

The following attributes are specific for library compilation:

Main module:

Project attributes (placed on top of the code in the Main module):

#LibraryName

- The compiled library name. Sets the library name.

#LibraryAuthor

- The library author. This value is added to the library xml file.

#LibraryVersion

- A number that represents the library version. This number will appear next to the library name in the libraries list.

Example, LimitBar projects.

B4A	B4i	B4J
<code>#LibraryName: LimitBar</code>	<code>#LibraryName: iLimitBar</code>	<code>#LibraryName: jLimitBar</code>
<code>#LibraryAuthor: Klaus Christl</code>	<code>#LibraryAuthor: Klaus Christl</code>	<code>#LibraryAuthor: Klaus Christl</code>
<code>#LibraryVersion: 1.0</code>	<code>#LibraryVersion: 1.0</code>	<code>#LibraryVersion: 1.0</code>

All modules:

#ExcludeFromLibrary - Whether to exclude this module during library compilation. Values: True or False. Note that the Main activity is always excluded.

CustomView classes:

#Event - Adds an event to the list of events. This attribute can be used multiple times. The parameters must be included.

Note that the events list only affects the IDE events autocompletion feature.

#RaisesSynchronousEvents - Needed if you compile the CustomView into a library.

It is used for the Rapid Debugger. You need one for each event.

Details in the LimitBar project [here](#).

Example, LimitBar projects.

```
#Event: ValuesChanged(LimitLeft As Int, LimitRight As Int)
#RaisesSynchronousEvents: ValuesChanged
ValuesChanged is the name of the event for its call.
```

If you have other modules in the same project which should not be in the library, you must add

```
#ExcludeFromLibrary: True
```


Notes

- You should right click on the libraries list and choose Refresh after a library update.
- CallSub / CallSubDelayed - The first parameter for these keywords is a reference to the target module. When working with modules that reside in a library you should pass the module reference and not the module name as string (this is the better way to reference all modules in all cases).
- Code obfuscation - Libraries can be obfuscated during library compilation. Strings will not be obfuscated in this mode.
- Services that host home screen widgets cannot be compiled into a library.

The library files are automatically saved in the Additional Libraries folder.

You can see it in the Libraries Manager Tab.

Right click somewhere in the Libraries Manager Tab and click on .



Example with the B4i LimitBar project.

The library name is the name you entered in `#LibraryName: iLimitBar`.

When you select the library, it moves on top of the list and shows the version number. You should not have the modules and the library in the same project!

When you declare a custom view, you must use the Module/Object name:

Library: iLimitBar Object: LimitBar

```
Private ltbTest, ltbTest1 As LimitBar
```

4.6 Program flow

Below a comparison of the program flow with two custom views, one added in the Designer and the other in the code.

B4A	B4i	B4J
0 Process_Globals	0 Process_Globals	0 Process_Globals
0 Globals	0 Application_Start	0 AppStart
0 Activity_Create	1 Class_Globals	1 Class_Globals
1 Class_Globals	1 Class Initialize	1 Class Initialize
1 Class Initialize	1 DesignerCreateView	1 DesignerCreateView
1 DesignerCreateView	1 Base_Resize	1 Base_Resize
2 Class_Globals	2 Class_Globals	2 Class_Globals
2 Class Initialize	2 Class Initialize	2 Class Initialize
2 AddToParent	2 AddToParent	2 AddToParent
0 Activity_Resume	0 Page1_Resize	0 MainForm_Resize
Turn device	Turn device	Resize Main Form
0 Activity_Pause	0 Page1_Resize	0 MainForm_Resize
1 Class_Globals	1 Base_Resize	1 Base_Resize
1 Class Initialize		
1 DesignerCreateView		
2 Class_Globals		
2 Class Initialize		
2 AddToParent		
0 Activity_Resume		
0 = Main		
1 = CustomView Designer		
2 = CustomView code		

Note: The B4A example project above has no Starter service module.

We notice that when we start the program the flow is the same in B4i and B4J but in B4A it is a bit different.

When we turn the B4i device or resize the B4J form the program flow is the same.
In B4A it is quite different.

In B4A, the Activity is destroyed and recreated.
In B4i and B4J, the layout remains and a Resize event is raised.

The advantage of adding custom views in the Designer, in B4i and B4J, is that it handles the resize event and reapplies the anchors and designer script (and variant changes).
In B4A this is also executed because the Activity is recreated at every change.
This is shown in the LimitBar projects.

4.7 Intellisense help


It is advised to add help comments in the code for the users of your library.

4.7.1 Comments before Sub Class_Globals

Comments before `Sub Class_Globals` are considered as the help header when the class is compiled to a Library.

```
'LimitBar CustomView class.
'This CustomView allows the user to set two limits with two cursors.
'The Min value is 0 and the Max value is 100.
'The Max value can be changed by the programmer.
Sub Class_Globals
```

Example with the [B4x Help Viewer](#) and the LimitBar library.




4.7.2 Comments before a routine

Comments before a routine are considered as intellisense help.

```
'Initializes the object.
'Callback = name of the calling module
'EventName = event name
'Example if added in the code:
'<code>lbtTest.Initialize(Me, "lbtTest")</code>
Public Sub Initialize(Callback As Object, EventName As String)
```

Type 'lbtTest.', the method and property list is displayed.




4.7.3 Comments before an event routine

Events declared on top of the code in the class module with `#Event:` are displayed as intellisense when the class is compiled to a Library.

```
'Custom View class LimitBar
'Events declaration
#Event: ValuesChanged(LimitLeft As Int, LimitRight As Int)
```

When you use the library in another project, type `'Public Sub '` (with a space at the end) and press on Tab to show the objects list.



Select `LimitBar`.



Select `ValuesChanged(LimitLeft As Int, LimitRight As Int)`.

```
Private Sub EventName_ValuesChanged(LimitLeft As Int, LimitRight As Int)
End Sub
```

The sub frame is added.

```
Private Sub l1bTest1_ValuesChanged(LimitLeft As Int, LimitRight As Int)
End Sub
```

Enter the LimitBar name and press Return and the sub frame is finished.

```
Private Sub l1bTest1_ValuesChanged(LimitLeft As Int, LimitRight As Int)
End Sub
```


4.8 Help tool

If you have the [B4x Help Viewer](#) you can look at the help for the library.


Example with the B4A LimitBar library.

Click on  to load LimitBar.xml.

And the result.



Then you can select any method, event or property in the list to show the help.



5 First example CustomButton

We will make a simple CustomButton.



The button has a transparent base Panel (B4A, B4i) / Pane (B4J) plus one Label with a Material Icon and a second Label with text.

The CustomButton can be added in the Designer or in the code.

The CustomButton has two events Click and LongClick.

B4J has no Click nor LongClick event, Click is called Action or MouseClicked.

I kept the Click name and added the LongClick event.

The code is kept simple and minimalistic, the main goal here is to show the principle. Feel free to add more properties and functionalities.

5.1 Event declarations

First, we declare the events on top of the code. Needed when the class is compiled to a library.

```
'CustomButton Class
#Event: Click
#Event: LongClick
#RaisesSynchronousEvents: Click
#RaisesSynchronousEvents: LongClick
```

5.2 Custom properties for the Designer

We have only one custom property: Text.

This is the text below the icon.

The other properties, like icon character and text color, are defined in the Designer or in the AddToParent routine.

The icon and text sizes are calculated in the class code according to the button height.

```
#DesignerProperty: Key: Text, DisplayName: Text, FieldType: String, DefaultValue: Text,
Description: Text at the bottom of the button.
```

5.3 Class help header

We add a header text, just before `Sub Class_Globals`, explaining the purpose of the button as a help for the user.

```
'CustomButton is a button based on a Panel with two Labels
'one with a Material Icon and the other with text.
'It has two events: Click and LongClick.
Sub Class_Globals
```

5.4 Global variables

We define the global variables below. There are some differences between the three operating systems.

B4A

```
Sub Class_Globals
  Private mEventName As String
  Private mCallback As Object
  Private mBase As Panel

  Private mLeft, mTop, mWidth, mHeight As Int
  Private mText, mIcon As String
  Private mIconTypeface As Typeface
  Private mTextColor As Int
  Private mIconTextSize, mTextSize As Float
  Private mTag As Object

  Private mLabel, mIconLabel As Label
  Private mParent As Panel
End Sub
```

B4i `Typeface` is replaced by `Font`.

```
Private mIconTypeface As Font
```

B4J `Typeface` is replaced by `Font`. For the color `Int` is replaced by `Paint`.

We add another variable for the LongClick event timing

```
Private mIconTypeface As Font
Private mTextColor As Paint
Private mClickTime As Long      'used to distinguish Click and LongClick
```

5.5 Initialize routine

We get the Callback module and EventName and initialize three default values.

B4A / B4i

```
Public Sub Initialize (Callback As Object, EventName As String)
    mEventName = EventName
    mCallBack = Callback

    mIcon = Chr(0xE859)
    mText = "Test"
    mTextColor = Colors.Black
End Sub
```

B4J the color is `fx.Colors.Black` instead of `Colors.Black`.

```
mTextColor = fx.Colors.Black
```

5.6 DesignerCreateView routine

Here we get the properties from the Designer.

We initialize mBase and add it to the parent view.

We need this because we use event routines of the base panel / pane.

Just setting mBase = Base does not enable to use events.

B4A

```
Public Sub DesignerCreateView (Base As Panel, Lbl As Label, Props As Map)
    mLeft = Base.Left
    mTop = Base.Top
    mWidth = Base.Width
    mHeight = Base.Height
    mIcon = Lbl.Text
    mText = Props.Get("Text")
    mBase.Initialize("mBase")
    mParent = Base.Parent
    mParent.AddView(mBase, mLeft, mTop, mWidth, mHeight)

    mTextColor = Lbl.TextColor
    mIconTypeface = Lbl.Typeface
    mTag = Base.Tag

    InitClass
End Sub
```

B4i `Typeface` is replaced by `Font`.

```
mIconTypeface = Lbl.Font
```

Plus, the `Base_Resize` routine.

B4J `Typeface` is replaced by `Font`.

```
mIconTypeface = Lbl.Font
```

Plus, the `Base_Resize` routine.

The `InitClass` routine is moved to the `Base_Resize` routine.

5.7 Base_Resize routine B4i / B4J only

The Base_Resize routine is called every time a resize is done.
Device orientation change in B4i or a Form resize in B4J.

B4i

```
Private Sub Base_Resize (Width As Double, Height As Double)
    mHeight = Height
    mWidth = Width
End Sub
```

B4J

```
Private Sub Base_Resize (Width As Double, Height As Double)
    mWidth = Width
    mHeight = Height
    mBase.PrefWidth = mWidth
    mBase.PrefHeight = mHeight

    InitClass
End Sub
```

5.8 AddToParent routine

This routine is needed when we add the CustomButton in the code.
We memorize the position, dimensions and properties.
And call InitClass

B4A / B4i

```
Public Sub AddToParent(Parent As Panel, Left As Int, Top As Int, Width As Int, Height
As Int, TextColor As Int, Icon As String, Text As String)
    mLeft = Left
    mTop = Top
    mWidth = Width
    mHeight = Height
    mParent = Parent

    mBase.Initialize("mBase")
    Parent.AddView(mBase, mLeft, mTop, mWidth, mHeight)

    mIcon = Icon
    mText = Text
    mTextColor = TextColor

    InitClass
End Sub
```

B4J Parent.AddView is relaced by Parent.AddNode.

```
Parent.AddNode(mBase, mLeft, mTop, mWidth, mHeight)
```

5.9 InitClass routine

Here we initialize the common part independent if the CustomButton is added in the Designer or in the code.

B4A

Private Sub InitClass

```
'calculate the dimensions of the internal Labels
Private lblLeft, lblWidth As Int
lblWidth = 2 * mHeight / 3 'icon Label width and height = 2/3 of button height
lblLeft = (mWidth - lblWidth) / 2

'initialize and add the icon Label
mIconLabel.Initialize("")
mIconTextSize = mHeight / 2 / GetDeviceLayoutValues.Scale 'B4A, B4i
mIconLabel.Typeface = mIconTypeface 'B4A
mIconLabel.TextSize = mIconTextSize 'B4A, B4J
mIconLabel.Gravity = Gravity.CENTER 'B4A
mIconLabel.TextColor = mTextColor
mBase.AddView(mIconLabel, lblLeft, 0, lblWidth, lblWidth) 'B4A, B4i
mIconLabel.Text = mIcon

'initialize and add the text Label
mLabel.Initialize("")
mTextSize = lblWidth / 3 / GetDeviceLayoutValues.Scale 'B4A, B4i
mLabel.TextSize = mTextSize 'B4A, B4J
mLabel.TextColor = mTextColor
mLabel.Gravity = Bit.Or(Gravity.CENTER_HORIZONTAL, Gravity.TOP) 'B4A
mBase.AddView(mLabel, 0, 2 * mHeight / 3, mWidth, mHeight / 3) 'B4A, B4i
mLabel.Text = mText
```

End Sub

'B4A means that this line is only for B4A and different from B4i and B4J.

'B4A, B4i means that this line is the same for B4A and B4i, but is different in B4J.

B4i**Private Sub InitClass**

```

'calculate the dimensions of the internal Labels
Private lblLeft, lblWidth As Int
lblWidth = 2 * mHeight / 3 'icon Label width and height = 2/3 of button height
lblLeft = (mWidth - lblWidth) / 2

'initialize and add the icon Label
mIconLabel.Initialize("")
mIconTextSize = mHeight / 2 / GetDeviceLayoutValues.Scale 'B4i, B4A
mIconFont = Font.CreateNew2(mIconFont.Name, mIconTextSize) 'B4i
mIconLabel.Font = mIconFont 'B4i, B4J
mIconLabel.TextAlignment = mIconLabel.ALIGNMENT_CENTER 'B4i
mIconLabel.TextColor = mTextColor
mBase.AddView(mIconLabel, lblLeft, 0, lblWidth, lblWidth) 'B4i, B4A
mIconLabel.Text = mIcon

'initialize and add the text Label
mLabel.Initialize("")
mTextSize = lblWidth / 3 / GetDeviceLayoutValues.Scale 'B4i, B4A
mLabel.Font = Font.CreateNew(mTextSize) 'B4i
mLabel.TextColor = mTextColor
mLabel.TextAlignment = mIconLabel.ALIGNMENT_CENTER 'B4i
mBase.AddView(mLabel, 0, 2 * mHeight / 3, mWidth, mHeight / 3) 'B4i, B4A
mLabel.Text = mText

```

End Sub

B4J**Private Sub InitClass**

```

'calculate the dimensions of the internal Labels
Private lblLeft, lblWidth As Int
lblWidth = 2 * mHeight / 3 'icon Label width and height = 2/3 of button height
lblLeft = (mWidth - lblWidth) / 2

'initialize and add the icon Label
mIconLabel.Initialize("")
mIconTextSize = mHeight / 2 'B4J
mIconLabel.Font = mIconFont 'B4J, B4i
mIconLabel.TextSize = mIconTextSize 'B4J, B4A
mIconLabel.Alignment = "CENTER" 'B4J
mIconLabel.TextColor = mTextColor
mBase.AddNode(mIconLabel, lblLeft, 0, lblWidth, lblWidth) 'B4J
mIconLabel.Text = mIcon

'initialize and add the text Label
mLabel.Initialize("")
mTextSize = lblWidth / 3 'B4J
mLabel.TextSize = mTextSize 'B4J, B4A
mLabel.TextColor = mTextColor
mLabel.Alignment = "TOP_CENTER" 'B4J
mBase.AddNode(mLabel, 0, 2 * mHeight / 3, mWidth, mHeight / 3) 'B4J
mLabel.Text = mText

```

End Sub

5.10 Click / LongClick event routines

The two event routines.

B4A / B4i

```
Private Sub mBase_Click
    If SubExists(mCallBack, mEventName & "_Click") = True Then
        CallSub(mCallBack, mEventName & "_Click")
    End If
End Sub
```

```
Private Sub mBase_LongClick
    If SubExists(mCallBack, mEventName & "_LongClick") = True Then
        CallSub(mCallBack, mEventName & "_LongClick")
    End If
End Sub
```

B4J

Very different, because the LongClick event doesn't exist in B4J.

```
Private Sub mBase_MousePressed (EventData As MouseEvent)
    mClickTime = DateTime.Now
End Sub
```

```
Private Sub mBase_MouseReleased (EventData As MouseEvent)
    If DateTime.Now - mClickTime < 500 Then
        If SubExists(mCallBack, mEventName & "_Click") = True Then
            CallSub(mCallBack, mEventName & "_Click")
        End If
    Else
        If SubExists(mCallBack, mEventName & "_LongClick") = True Then
            CallSub(mCallBack, mEventName & "_LongClick")
        End If
    End If
End Sub
```

In `mBase_MousePressed`, we memorize the time when the mouse is pressed.

In `mBase_MouseReleased`, we check the time elapsed between press and release.

If the time is less than 500 milli-seconds, then we admit a Click and if time is longer we admit a LongClick event.

5.11 Property routines

Below the routine to set the IconTypeFace / IconFont property.

B4A

```
'set the icon typeface  
'must be FontAwesome or Material Icons  
Public Sub setIconTypeface(IconTypeface As Typeface)  
    mIconTypeface = IconTypeface  
End Sub
```

B4i / B4J

```
'set the icon typeface  
'must be FontAwesome or Material Icons  
Public Sub setIconFont(IconFont As Font)  
    mIconFont = IconFont  
End Sub
```

And the Tag property.

B4A / B4i / B4J

```
'get or set the Tag property  
Public Sub setTag(Tag As Object)  
    mTag = Tag  
    mBase.Tag = Tag  
End Sub  
  
Public Sub getTag As Object  
    Return mTag  
End Sub
```

I haven't added other properties to not overload the code.

5.12 Main code

5.12.1 Globals

Only two variables, in addition to the default declarations in B4i and B4J.

B4A / B4i B4J


```
Sub Globals
    Private cbtTest10 As CustomButton
    Private lblDummy As Label
End Sub
```

We need a dummy invisible Label to get the Material Icons Typeface / Font for the icon Label when the CustomButton is added in the code.

B4A



B4i / B4J



5.12.2 Program start

B4A

```
Sub Activity_Create(FirstTime As Boolean)
    Activity.LoadLayout("Main")

    cbtTest10.Initialize(Me, "cbtTest")
    cbtTest10.IconTypeface = lblDummy.Typeface
    cbtTest10.AddToParent(Activity, 20dip, 200dip, 60dip, 60dip, Colors.RGB(0, 0, 139),
Chr(0xE149), "Test 10")
    cbtTest10.Tag = 10
End Sub
```

B4i

```
Private Sub Application_Start (Nav As NavigationController)
    NavControl = Nav
    Page1.Initialize("Page1")
    Page1.Title = "Page 1"
    Page1.RootPanel.Color = Colors.White
    Page1.RootPanel.LoadLayout("Main")
    NavControl.ShowPage(Page1)

    cbtTest10.Initialize(Me, "cbtTest")
    cbtTest10.IconFont = lblDummy.Font
    cbtTest10.AddToParent(Page1.RootPanel, 30, 100, 60, 60, Colors.RGB(0, 0, 139),
Chr(0xE05C), "Test 10")
    cbtTest10.Tag = 10
End Sub
```

B4J

```
Sub AppStart (Form1 As Form, Args() As String)
    MainForm = Form1
    MainForm.RootPane.LoadLayout("Main") 'Load the layout file.
    MainForm.Show

    MainForm.Title = "jClsCustomButton"

    cbtTest10.Initialize(Me, "cbtTest")
    cbtTest10.IconFont = lblDummy.Font
    cbtTest10.AddToParent(MainForm.RootPane, 100, 100, 60, 60, fx.Colors.RGB(0, 0, 139),
Chr(0xE05C), "Test 10")
    cbtTest10.Tag = 10
End Sub
```

Besides the default operating system methods, the CustomButton declaration is also a bit different.

- Parent object: **B4A** Activity (Panel), **B4i** Page1.RootPanel, **B4J** MainForm.RootPane.
- Font type:
 - B4A** Typeface
cbtTest10.IconTypeface = lblDummy.Typeface
 - B4i / B4J** Font
cbtTest10.IconFont = lblDummy.Font

5.13 Click event routine

The Click event routine is the same for all three operating systems:

```
Private Sub cbtTest_Click
    Private cbt As CustomButton
    Private Index As Int

    cbt = Sender
    Index = cbt.Tag

    Select Index
    Case 1
        Log("cbtTest1_Click")
    Case 2
        Log("cbtTest2_Click")
    Case 10
        Log("cbtTest10_Click")
    Case Else
        Log("cbtTest" & Index & "_Click")
    End Select
End Sub
```

I set the same event name for all CustomButtons and use the Tag property of the Sender object to know which button raised the event.

The LongClick event routine is almost the same, `LongClick` replaces `Click`.

5.14 Compile to Library

We add the library declarations on top of the code in the Main module.

B4A

```
#LibraryName: CustomButton  
#LibraryAuthor: Klaus CHRISTL  
#LibraryVersion: 1.0
```

B4i

```
#LibraryName: iCustomButton  
#LibraryAuthor: Klaus CHRISTL  
#LibraryVersion: 1.0
```

B4J

```
#LibraryName: jCustomButton  
#LibraryAuthor: Klaus CHRISTL  
#LibraryVersion: 1.0
```

And we compile the CustomButton module to a Library.

The Library files are automatically copied to the AdditionalLibraries folder.


If you use the hosted compiler for B4i, you must [ask Erel for permission](#) to be able to compile a library.

5.15 Use the library in a program


Copy the projects to new folders where you replace *Cls* by *Lib*.
The source codes are in the *LibCustomButton* folders

Then:

- Load the projects in the IDE.
- Rename the package name.
- Rename the `#ApplicationLabel: LblCustomButton` (B4A and B4i only)
- Remove the three lines:
`#LibraryName: CustomButton`
`#LibraryAuthor: Klaus CHRISTL`
`#LibraryVersion: 1.0`
- Remove the CustomButton class module.
Select the CustomButton module and remove it.



- Select the CustomButton library in the Libraries Manager Tab.



- Run the program.

The rest of the code in the Main module remains the same.
The layout file remains the same.

6 LimitBar

Another concrete example, a LimitBar.

The LimitBar looks like this, images from the B4A project:



Two cursors allow to define two limits between 0 and a max value.

In the demo program, we add two labels, one on each side, to display the two limit values these are not part of the custom view.



There are two projects for each operating system:

- ClsLimitBarDemo, project with the custom view class module.
- LibLimitBarDemo, project with the custom view as a library (class module compiled to a library).

It supports adding a LimitBar in the Designer or in the code.

In the demo projects two LimitBars are added, one in the Designer and one in the code.

The source codes are in the \ClsLimitBar and \LibLimitBar folders, one folder for each operating system.

We use for:

B4A / B4i

Two panels:

- `ltbPanelBack` the background with the background color and the red 'background' line.



- `ltbPanelFront` the foreground, transparent with the 'foreground' line and the two cursors.



and two canvases:

- `cvsPanelBack` to draw the background line onto `ltbPanelBack`.
- `cvsPanelFront` to draw the foreground line and the cursors onto `ltbPanelFront`.

B4J

One pane as the custom view holder `ltbPanelBack` and two canvases `cvsBack` and `cvsFront`.

The difference in B4J is that canvases are objects on their own, not linked to another object like in B4A and B4i.

The LimitBar customView raises one event:

```
ValuesChanged(LimitLeft As Int, LimitRight As Int)
```

In the next chapters, the code is explained from top to down.

6.1 Event declaration

On top of the code we declare the event:

```
'Events declaration
#Event: ValuesChanged(LimitLeft As Int, LimitRight As Int)
#RaisesSynchronousEvents: ValuesChanged
```

We need this for the [intellisense system](#) when the class module is compiled to a library.

6.2 Custom properties for the Designer

The LimitBar has following custom properties:

- Max
Sets or gets the max limit value when the cursor is at the most right position.
The default value is 100.
- LimitLeft
Sets or gets the left limit value. The default value is 0.
- LimitRight
Sets or gets the right limit value. The default value is 100.
- BackLineColor
Sets or gets the back-line color. The default value is red (0xFFFF0000).
- FrontLineColor
Sets or gets the front-line color. The default value is light blue (0x FF33B5E5).

To support setting these properties in the Designer we must declare them:

```
'Designer property declarations
#DesignerProperty: Key: Max, DisplayName: Max, FieldType: Int, DefaultValue: 100,
Description: Sets the max value.
#DesignerProperty: Key: LimitLeft, DisplayName: Left limit, FieldType: Int,
DefaultValue: 10, Description: Sets the left limit value.
#DesignerProperty: Key: LimitRight, DisplayName: Right limit, FieldType: Int,
DefaultValue: 100, Description: Sets the right limit value.
#DesignerProperty: Key: Radius, DisplayName: Radius, FieldType: Int, DefaultValue: 5,
Description: Sets the corner radius.
#DesignerProperty: Key: BackgroundColor, DisplayName: BackgroundColor, FieldType:
Color, DefaultValue: 0xFF0000FF, Description: Sets the background color.
#DesignerProperty: Key: BackLineColor, DisplayName: BackLineColor, FieldType: Color,
DefaultValue: 0xFFFF0000, Description: Sets the back line color.
#DesignerProperty: Key: FrontLineColor, DisplayName: FrontLineColor, FieldType: Color,
DefaultValue: 0xFF33B5E5, Description: Sets the front line color.
```

We will add also code to set or get these properties in the code.

6.3 Class help header

Class header help text, just before `Sub Class_Globals`.

```
'LimitBar CustomView class.
'This CustomView allows the user to set two limits with two cursors.
'The Min value is 0 and the Max value is 100.
'The Max value can be changed by the programmer.
Sub Class_Globals
```

6.4 Global variables

In `Sub Class_Globals` we declare the objects and variables.

B4A / B4i the only difference is `cdwBackground As ColorDrawable` used in B4A.

`Sub Class_Globals`

```
Private mCallback As Object      ' calling module
Private mEventName As String    ' event name
Private mWidth, mHeight, mRadius As Int

Private ltbPanelBack As Panel    ' the background panel
Private ltbPanelFront As Panel  ' the foreground panel
Private cvsPanelBack As Canvas  ' the background canvas
Private cvsPanelFront As Canvas ' the foreground canvas
Private rectPanelFront As Rect  ' a rectangle for the foreground canvas

Private mBackgroundColor As Int  ' color for the background
Private cdwBackground As ColorDrawable ' background drawable, only for B4A
Private mBackLineColor As Int   ' color for the background line
Private mFrontLineColor As Int  ' color for the foreground line
Private mMargin As Int          ' left and right margins for the line
Private x0, y0, x1, y1, y2 As Int ' backline and cursor coordinates
Private mMaxValue As Int        ' value of the Max property
Private mScale As Double        ' scale between position value and pixels
Private mLimit(2) As Int        ' values of the limits
Private PositionPixels(2) As Int ' left and right positions in pixels
Private Paths(2) As Path        ' two paths for the cursor shape
Private PosIndex As Int         ' current index of the cursor position
                                ' 0 = left 1 = right cursor
```

`End Sub`

B4J

`Sub Class_Globals`

```
Private fx As JFX                ' B4J specific
Private mCallback As Object      ' calling module
Private mEventName As String     ' event name
Private mWidth, mHeight, mRadius As Double

Private ltbPanelBack As Pane     ' the background pane
Private cvsBack As Canvas        ' the background canvas
Private cvsFront As Canvas       ' the foreground canvas

Private mBackgroundColor As Paint ' color for the background
Private mBackLineColor As Paint  ' color for the background line
Private mFrontLineColor As Paint  ' color for the foreground line
Private mMargin As Double        ' left and right margins for the line
Private x0, y0, x1, y1, y2 As Double ' backline and cursor coordinates
Private mMaxValue As Int         ' value of the Max property
Private mScale As Double        ' scale between position value and pixels
Private mLimit(2) As Int        ' value of the limits
Private PositionPixels(2) As Double ' left and right positions in pixels
Private PosIndex As Int         ' 0 = left 1 = right

Private Graph, jCanvasFront As JavaObject ' B4J specific used to draw the cursors
```

`End Sub`

There are some differences between B4J and B4A / B4i. B4J needs of the `jFX` library. Some differences for the canvases. No foreground panel but two `JavaObjects`.

6.5 Initialize routine

Then we need the routine to initialize the LimitBar, the code is self explanatory. This routine is automatically called if you add the LimitBar in the Designer. If you add the LimitBar in the code, you must call this routine first. You should not modify the signature of this routine

B4A / B4i / B4J

```
'Initializes the object.
'Callback = name of the calling module
'EventName = event name
'Example if added in the code:
'<Code>ltbTest.Initialize(Me, "ltbTest")'</Code>
Public Sub Initialize(Callback As Object, EventName As String)
    mCallback = Callback
    mEventName = EventName

    ' initialize default values
    mBackgroundColor = Colors.Blue
    mBackColor = Colors.Black
    mFrontLineColor = Colors.RGB(51, 181, 229)
    mMargin = 15
    mMaxValue = 100
    mLimit(0) = 0
    mLimit(1) = mMaxValue
End Sub
```

6.6 DesignerCreateView routine

Then we have the DesignerCreateView routine.

This routine is called automatically after Initialize when the LimitBar is added in the Designer.

It is NOT used when you add the LimitBar in the code.

B4A / B4i

```
Public Sub DesignerCreateView(Base As Panel, Lbl As Label, Props As Map)
    ' we use the Base panel as the background panel
    ltbPanelBack = Base

    ' we memorize the Base Width and Height properties
    mWidth = Base.Width
    mHeight = Base.Height

    ' we memorize the custom properties
    mMaxValue = Props.Get("Max")
    mLimit(0) = Props.Get("LimitLeft")
    mLimit(0) = Max(0, mLimit(0)) ' we check the min value, not less than 0

    mLimit(1) = Props.Get("LimitRight")
    mLimit(1) = Min(mMaxValue, mLimit(1)) ' we check the max value, not higher than Max

    mRadius = Props.Get("Radius")
    mBackgroundColor = Props.Get("BackgroundColor")
    mBackLineColor = Props.Get("BackLineColor")
    mFrontLineColor = Props.Get("FrontLineColor")

    InitClass ' initializes the common parts for Designer and code
End Sub
```

We use the Base Panel with the name ltbPanelBack, and get the custom properties from the Props Map object.

As the LimitBar custom view can also be added in the code we initialize the rest in the InitClass routine.

B4J at end of the routine with B4i specific code.

```
mBackLineColor = Props.Get("BackLineColor")
mFrontLineColor = Props.Get("FrontLineColor")
End Sub
```

The InitClass routine is moved to a B4J specific routine **Base_Resize**:

Note that the signature of the routine is different:

```
Public Sub DesignerCreateView(Base As Panel, Lbl As Label, Props As Map)
```

Base As Pane instead of Base As Panel.

6.7 Base_Resize routine B4i / B4J only

In B4i and B4J there is a specific routine `Private Sub Base_Resize`. This routine is executed every time a resize is operated.

B4i

```
Private Sub Base_Resize (Width As Double, Height As Double)
    setWidth(Width)
End Sub
```

B4J

```
Private Sub Base_Resize (Width As Double, Height As Double)
    mWidth = ltbPanelBack.Width
    mHeight = ltbPanelBack.Height

    If cvsBack.IsInitialized = False Then
        InitClass      ' initializes the common parts for Designer and code
    End If
    setWidth(Width)
End Sub
```

In B4J the width and height of the Base pane is known only in the `Base_Resize` routine. This routine is called directly after `DesignerCreateView` when the LimitBar is added in the Designer.

It is not called when the LimitBar is added in the code.

6.8 AddToParent routine

The AddToParent routine.

This routine must be called when you add the LimitBar in the code.

It is not used when the LimitBar is added in the Designer.

B4A / B4i / B4J

```
'Adds the LimitBar to the Parent object
'Parent = parent view, the Activity or a Panel
'Left, Right, Width, Height = position and dimensions properties of the LimitBar
'Color = background color of the LimitBar
'Radius = corner radius of the LimitBar
Public Sub AddToParent(Parent As Activity, Left As Int, Top As Int, Width As Int,
Height As Int, BackgroundColor As Int, Radius As Int)
    mWidth = Width
    mHeight = Max(Height, 30dip)           ' limits the height to min 30dip
    mRadius = Min(Radius, Height / 2)     ' limits the max radius to half the height
    mBackgroundColor = BackgroundColor

    ' initialize the background panel ltbPanelBack and add it onto the parent view
    ltbPanelBack.Initialize("")
    Parent.AddView(ltbPanelBack, Left, Top, Width, Height)

    InitClass ' initializes the common parts for Designer and code
End Sub
```

We memorize several properties, initialize ltbPanelBack and add it onto the parent view and set its background and call InitClass.

Example:

```
'adds a second LimitBar in the code
ltbTest1.Initialize(Me, "ltbTest1")
ltbTest1.FrontLineColor = Colors.Blue
ltbTest1.AddToParent(Activity, 30dip, 100dip, 200dip, 30dip, Colors.Red, 5dip)
```

6.9 InitClass routine

In this routine, we initialize the common code parts independent if the LimitBar is added in the Designer or in the code.

This routine is called either from the **DesignerCreateView** when the LimitBar is added in the Designer or from the **AddToParent** routine when the custom view is added in the code.

B4A

Private Sub InitClass

```
InitCursors
```

```
' initialize and set the ColorDrawable for the background panel
```

```
cdwBackground.Initialize(mBackgroundColor, mRadius)
```

```
ltbPanelBack.Background = cdwBackground
```

```
' initialize the foreground panel and add it onto the background panel
```

```
ltbPanelFront.Initialize("ltbPanelFront")
```

```
ltbPanelBack.AddView(ltbPanelFront, 0, 0, ltbPanelBack.Width, ltbPanelBack.Height)
```

```
' initialize the foreground panel rectangle used to erase ltbPanelFront
```

```
rectPanelFront.Initialize(0, 0, ltbPanelFront.Width, ltbPanelFront.Height)
```

```
ltbPanelFront.BringToFront
```

```
' initialize the background canvas and draw the background line
```

```
cvsPanelBack.Initialize(ltbPanelBack)
```

```
DrawBackgroundLine
```

```
' initialize the foreground canvas
```

```
cvsPanelFront.Initialize(ltbPanelFront)
```

```
' set the limit max value, which calculates also the scale limit values <> pixels
```

```
setMax(mMaxValue)
```

```
End Sub
```

The code is self explanatory.

B4i The background color setting is different from B4A.

Private Sub InitClass

InitCursors

' set the background color and the radius for the background panel

ltbPanelBack.Color = mBackgroundColor

ltbPanelBack.SetBorder(0, mBackgroundColor, mRadius)

' initialize the foreground panel and add it onto the background panel

ltbPanelFront.Initialize("ltbPanelFront")

ltbPanelBack.AddView(ltbPanelFront, 0, 0, ltbPanelBack.Width, ltbPanelBack.Height)

' initialize the foreground panel rectangle used to erase ltbPanelFront

rectPanelFront.Initialize(0, 0, ltbPanelFront.Width, ltbPanelFront.Height)

ltbPanelFront.BringToFront

' initialize the background canvas and draw the background line

cvsPanelBack.Initialize(ltbPanelBack)

DrawBackGroundLine

' initialize the foreground canvas

cvsPanelFront.Initialize(ltbPanelFront)

setMax(mMaxValue)

End Sub

B4J the code is somewhat more specific.

Private Sub InitClass

InitCursors

```
' set the background color and the radius for the background panel
CSSUtils.SetBackgroundColor(ltbPanelBack, mBackgroundColor)
CSSUtils.SetBorder(ltbPanelBack, 0, mBackgroundColor, mRadius)

' initialize the background canvas and draw the background line
cvsBack.Initialize("cvsBack")
ltbPanelBack.AddNode(cvsBack, 0, 0, mWidth, mHeight)
DrawBackGroundLine

' initialize the foreground canvas
cvsFront.Initialize("cvsFront")
ltbPanelBack.AddNode(cvsFront, 0, 0, mWidth, mHeight)

' set a JavaObject for CanvasFront, needed for the drawing of the cursors
jCanvasFront = cvsFront
Graph = jCanvasFront.RunMethod("getGraphicsContext2D", Null)

' set the limit max value, which calculates also the scale limit values <> pixels
setMax(mMaxValue)
```

End Sub

To set the background color and corner radius we need the CSSUtils library.

We initialize the back and front canvases and add them to the base pane.

As there is no direct Path object in B4J to draw the cursors we use a JavaObject Graph for this and initialize it here.

6.10 InitCursors routine

In this routine, we initialize the variables used for the background line and the cursors drawing.


B4A / B4i / B4J

Private Sub InitCursors

```
x0 = mMargin  
x1 = mWidth - mMargin  
mScale = (x1 - x0) / mMaxValue  
PositionPixels(0) = mLimit(0) * mScale + x0  
PositionPixels(1) = mLimit(1) * mScale + x0
```

```
y0 = 0.2 * mHeight  
y1 = y0 + 8dip + 0.05 * mHeight  
y2 = 0.9 * mHeight
```

End Sub



6.11 Draw the background line

We need to draw the background color and background line from several places in the code so we use a routine.

B4A

```
Private Sub DrawBackground
    ltbPanelBack.Background = cdwBackground
    cvsPanelBack.Initialize(ltbPanelBack)
    cvsPanelBack.DrawLine(x0, y0, x1, y0, mBackLineColor, 2dip)
    ltbPanelBack.Invalidate
End Sub
```

We set the background of ltbPanelBack.

Reinitialize the background canvas, needed when the dimensions of ltbPanelBack change.

Draw the background line.

Force ltbPanelBack to redraw.

ltbPanelBack.Invalidate is equivalent to cvsPanelBack.Refresh in B4i.

B4i

```
Private Sub DrawBackground
    cvsPanelBack.Initialize(ltbPanelBack)
    cvsPanelBack.DrawRectRounded(rectPanelFront, mBackgroundColor, True, 1, mRadius)
    cvsPanelBack.DrawLine(x0, y0, x1, y0, mBackLineColor, 2dip)
    cvsPanelBack.Refresh
End Sub
```

Reinitialize the background canvas, needed when the dimensions of ltbPanelBack change.

Draw the background onto the canvas.

Draw the background line.

Force ltbPanelBack to redraw.

cvsPanelBack.Refresh is equivalent to ltbPanelBack.Invalidate in B4A.

B4J

```
Private Sub DrawBackground
    cvsBack.ClearRect(0, 0, mWidth, mHeight)
    cvsBack.DrawLine(x0, y0, x1, y0, mBackLineColor, 2)
End Sub
```

The background color is on the base pane.

So, we set the background canvas to transparent.

Draw the background line.

No need for ltbPanelBack.Invalidate nor cvsPanelBack.Refresh to redraw the canvas.

6.12 DrawCursors routine

The drawing routine for the cursors and the foreground line:

We use two Path objects to draw the cursor shapes.

B4A / B4i

Private Sub DrawCursors

```
' draw a transparent rectangle to erase the foreground panel
cvsPanelFront.DrawRect(rectPanelFront, Colors.Transparent, True, 1)

' define the left cursor path according to its current position
Paths(0).Initialize(PositionPixels(0), y0)
Paths(0).LineTo(PositionPixels(0), y2)
Paths(0).LineTo(PositionPixels(0) - 12dip, y2)
Paths(0).LineTo(PositionPixels(0) - 12dip, y1)
Paths(0).LineTo(PositionPixels(0), y0)

' define the right cursor path according to its current position
Paths(1).Initialize(PositionPixels(1), y0)
Paths(1).LineTo(PositionPixels(1), y2)
Paths(1).LineTo(PositionPixels(1) + 12dip, y2)
Paths(1).LineTo(PositionPixels(1) + 12dip, y1)
Paths(1).LineTo(PositionPixels(1), y0)

' draw the two cursors and the front line
cvsPanelFront.DrawPath(Paths(0), mFrontLineColor, True, 1)
cvsPanelFront.DrawPath(Paths(1), mFrontLineColor, True, 1)
cvsPanelFront.DrawLine(PositionPixels(0), y0, PositionPixels(1), y0, mFrontLineColor,
3dip)

ltbPanelFront.Invalidate
End Sub
```

We:

- Erase the whole panel by drawing a transparent rectangle.
- Define both cursors according to the current position.
The cursor shapes are defined with two Paths.
- Draw the cursors.
- Draw the foreground line.

The only difference between B4A and B4i is the redraw method at the end of the routine:

```
B4A ltbPanelFront.Invalidate
B4i cvsPanelFront.Refresh
```

B4J the routine is different because the Path object doesn't exist like in B4A / B4i. The path methods are different and not directly exposed to B4J, but we can use those with the JavaObject Graph which is defined in the InitClass routine.

Private Sub DrawCursors

```
' draw a transparent rectangle to erase the foreground panel
cvsFront.ClearRect(0, 0, cvsFront.Width, cvsFront.Height)

' draw the left cursor
Graph.RunMethod("setFill", Array As Object(mFrontLineColor))
Graph.RunMethod("beginPath", Null)
Graph.RunMethod("moveTo", Array As Object(PositionPixels(0), y0))
Graph.RunMethod("lineTo", Array As Object(PositionPixels(0), y2))
Graph.RunMethod("lineTo", Array As Object(PositionPixels(0) - 12, y2))
Graph.RunMethod("lineTo", Array As Object(PositionPixels(0) - 12, y1))
Graph.RunMethod("fill", Null)

' draw the right cursor
Graph.RunMethod("setFill", Array As Object(mFrontLineColor))
Graph.RunMethod("beginPath", Null)
Graph.RunMethod("moveTo", Array As Object(PositionPixels(1), y0))
Graph.RunMethod("lineTo", Array As Object(PositionPixels(1), y2))
Graph.RunMethod("lineTo", Array As Object(PositionPixels(1) + 12dip, y2))
Graph.RunMethod("lineTo", Array As Object(PositionPixels(1) + 12dip, y1))
Graph.RunMethod("fill", Null)

' draw the front line
cvsFront.DrawLine(PositionPixels(0), y0, PositionPixels(1), y0, mFrontLineColor,
3dip)
End Sub
```

6.13 Cursor moving

To detect cursor moves we use the touch event of the foreground panel in B4A / B4i and the mouse events of the front canvas in B4J:

B4A / B4i same routine

```

Private Sub ltbPanelFront_Touch (Action As Int, X As Float, Y As Float)
    ' check if the cursor is outside the limits
    X = Max(x0, X)
    X = Min(x1, X)

    ' select the Action type
    Select Action
    Case 0 'DOWN
        If X < Abs(PositionPixels(0) + PositionPixels(1)) / 2 Then
            ' if X is closer to the left cursor we choose it
            PosIndex = 0
        Else
            ' otherwise we choose the right cursor
            PosIndex = 1
        End If
        mLimit(PosIndex) = Floor((X - x0) / mScale + .5)
        PositionPixels(PosIndex) = X
        DrawCursors
    Case 2 ' MOVE
        mLimit(PosIndex) = Floor((X - x0) / mScale + .5)
        PositionPixels(PosIndex) = X
        DrawCursors
    Case 1 ' UP
        ' when Action is UP (mouse released) check if mLimit(0) > mLimit(1)
        ' if yes we invert the limit values and redraw the cursors
        If mLimit(0) > mLimit(1) Then
            Private val As Int
            val = mLimit(0)
            mLimit(0) = mLimit(1)
            mLimit(1) = val
            PositionPixels(0) = mLimit(0) * mScale + x0
            PositionPixels(1) = mLimit(1) * mScale + x0
            DrawCursors
        End If
    End Select

    ' if a callback routine exists in the calling module we call it
    If SubExists(mCallback, mEventName & "_ValuesChanged") Then
        CallSub3(mCallback, mEventName & "_ValuesChanged", mLimit(0), mLimit(1))
    End If
End Sub

```

B4J very different because the Touch event doesn't exist in B4J and we must use the mouse event routines. But, as we have a routine handling the Touch event in B4A and B4i we use the same routine and call it from the mouse event routines.

Mouse event routines:

- MouseClicked equivalent to the Click event.
- MouseDragged equivalent to the Touch event MOVE with a button pressed.
- MouseMoved no equivalent in B4A / B4i MOVE but no button pressed.
- MousePressed equivalent to the Touch event DOWN.
- MouseReleased equivalent to the Touch event UP.

These routines return a MouseEvent object with following properties.

- ClickCount
- Consume
- MiddleButtonDown
- MiddleButtonPressed
- PrimaryButtonDown
- PrimaryButtonPressed
- SecondaryButtonDown
- SecondaryButtonPressed

We use the MousePressed (DOWN), MouseDragged (MOVE) and MouseReleased (UP) events.

```
Private Sub cvsFront_MousePressed (EventData As MouseEvent)
    cvsFront_Touch (0, EventData.X)
End Sub
```

```
Private Sub cvsFront_MouseDragged (EventData As MouseEvent)
    cvsFront_Touch (2, EventData.X)
End Sub
```

```
Private Sub cvsFront_MouseReleased (EventData As MouseEvent)
    cvsFront_Touch (1, EventData.X)
End Sub
```

And another routine which is internally exactly the same as the Touch event routine in B4A / B4i.

The only difference is its signature. `Private Sub cvsFront_Touch (Action As Int, X As Double)`

Instead of `Private Sub 1tbPanelFront_Touch (Action As Int, X As Float, Y As Float)`.

We transmit the 'Action' parameter and only the X coordinate because we don't need the Y coordinate.

6.14 Properties

Finally, we add a few properties:

To add properties, see more details in [Add properties](#).

The Max property:

```
'gets or sets the max value
Sub setMax(cMax As Int)
    MaxVal = cMax
    Scale = (x1 - x0) / MaxVal
End Sub

Sub getMax As Int
    Return MaxVal
End Sub
```

The LimitLeft property:

```
'gets or sets the left limit
Sub setLimitLeft(Pos As Int)
    ' if Pos is lower than 0 set cLimitLeft to 0
    cLimitLeft = Max(0, Pos)
    PosIndex = 0
    DrawPos(x0 + cLimitLeft * Scale, 0)
End Sub

Sub getLimitLeft As Int
    Return cLimitLeft
End Sub
```

The LimitRight property:

```
'gets or sets the right limit
Sub setLimitRight(Pos As Int)
    ' if Pos is higher than MaxVal set cLimitRight to MaxVal
    cLimitRight = Min(MaxVal, Pos)
    PosIndex = 1
    DrawPos(x0 + cLimitRight * Scale, 0)
End Sub

Sub getLimitRight As Int
    Return cLimitRight
End Sub
```

The Visible property:

```
'gets or sets the Visible property
Sub setVisible(IsVisible As Boolean)
    ltbPanelBack.Visible = IsVisible
End Sub

Sub getVisible As Boolean
    Return ltbPanelBack.Visible
End Sub
```

I didn't add more properties to keep the example code 'simple'.
But other properties could easily be added.

6.15 Compile to a Library

In the Project Attributes Region in the Main module we add following new attributes:

Example, LimitBar projects.

B4A	B4i	B4J
<code>#LibraryName: LimitBar</code>	<code>#LibraryName: iLimitBar</code>	<code>#LibraryName: jLimitBar</code>
<code>#LibraryAuthor: Klaus Christl</code>	<code>#LibraryAuthor: Klaus Christl</code>	<code>#LibraryAuthor: Klaus Christl</code>
<code>#LibraryVersion: 1.0</code>	<code>#LibraryVersion: 1.0</code>	<code>#LibraryVersion: 1.0</code>

And we compile the Limitbar module to a Library.

The Library files are automatically copied to the AdditionalLibraries folder.

If you use the hosted compiler for B4i, you must [ask Erel for permission](#) to be able to compile a library.

6.15.1 Using the library in a program


Copy the projects to new folders where you replace *Cls* by *Lib*.
The source codes are in the *LibLimitBar* folders.

Then:


- Load the projects in the IDE.
- Rename the package name.
- Rename the `#ApplicationLabel: LblLimitBar` (B4A and B4i only)
- Remove the three lines:

```
#LibraryName: LimitBar
#LibraryAuthor: Klaus CHRISTL
#LibraryVersion: 1.0
```

- Remove the LimitBar class module.
Select the LimitBar module and remove it.



- Select the LimitBar library in the Libraries Manager Tab.



- Run the program.

The rest of the code in the Main module remains the same.
The layout file remains the same.